

WACKY MCLOVIN

Stream Boards Setup Guide

Put a big, bright game board behind you on TikTok LIVE. Set it up in about 10 minutes. No tech skills needed.

WACKY HUNT **PRE-FILL** **LIVE** **\$10 A SPOT**

EVERY SPOT GETS A PACK

1 ripking	CHASE  ALT ART CHASE CARD \$450 CARD PULLING FROM OP-11 BOOSTER BOX	13 pikapull
2 jonah_m		14 onepiece_ot
3 cardqueen		15 OPEN
4 tcgdad		16 OPEN
5 slabhunter		17 bigboxbob
6 OPEN		18 OPEN
7 packmaster		19 hitseeker
8 luffy_fan	13/24 11 OPEN	20 OPEN
9 OPEN		21 OPEN
10 goldrush		22 OPEN
11 mintcondition		23 OPEN
12 OPEN		24 OPEN

GEAR CHECKLIST

10 MINUTE SETUP

8 GAMES

SHOP ORDERS + LABELS

BEST SETTINGS

Boards: boards.wackymclov.in

Help: boards.wackymclov.in/how-to

1 *What you need*

Check off each box. You probably have most of this already.

MUST HAVE

- ☐ **A phone to go live**
Any newer iPhone or Android. Use the back camera.
- ☐ **A phone tripod or mount**
Holds the phone steady at chest height.
- ☐ **A TV or monitor**
40 inches or bigger is best. 24 to 32 inches works on a small table.
- ☐ **Something to open the board on the TV**
A laptop and HDMI cable, a mini PC, or a smart TV web browser.
- ☐ **Good internet**
At least 10 Mbps upload. Use a cable if you can.
- ☐ **A free Google account**
Your game sheet lives here.

NICE TO HAVE

- ☐ **A ring light or LED light**
Put it in front of you, never behind you.
- ☐ **A second screen for your sheet**
A tablet, laptop, or old phone to type names.
- ☐ **A label printer (for shop orders)**
Any 4x6 thermal shipping printer: Rollo, MUNBYN, Phomemo, or Zebra. Small stickers: DYMO LabelWriter or Brother QL.
- ☐ **Labels that fit your printer**
4x6 shipping labels work great.
- ☐ **A computer for OBS or TikTok LIVE Studio**
Only if you want the board inside your video. A phone is fine to start.
- ☐ **A phone charger and long cable**
Streams run long. Stay plugged in.


CAN I GO LIVE ON TIKTOK?

TikTok sets its own rules. In 2026 that's usually: 18 or older, about 1,000 followers (it can change by country), and no recent rule strikes. Selling on LIVE with TikTok Shop can need its own approval. Open TikTok, tap +, and swipe to **LIVE**. If you see the Go LIVE button, you're good.

2 *Set up your table*

Where everything goes, and the settings that make the board look sharp.

HOW TO SET UP YOUR TABLE



BEST SETTINGS

THING	SET IT TO	WHY
TV picture mode	Standard or Game. Motion smoothing OFF.	Text stays sharp on camera.
TV brightness	About 60%	Too bright looks washed out.
Browser zoom	100%, full screen	The board sizes itself.
Phone camera	Back camera, 1080p, 30 fps	Sharp, smooth, stays cool.
Phone focus	Tap and hold on the TV to lock it	Stops the picture from pulsing.
Phone	Plugged in. Do Not Disturb on.	No dead battery, no pop-ups.
Internet	10 Mbps upload or more	No freezing.
OBS (optional)	Browser Source, paste the board's OBS link. 1920 x 1080, or 1080 x 1920 for vertical.	Puts the board inside your video.

3 *The 10 minute setup*

Do these once. After that, you just open your bookmark and go.

- 1** **Copy your game sheet.** Go to **boards.wackymclovin.com/downloads** and click **Copy** on the sheet you want. Google makes your own copy.
- 2** **Share it so the board can read it.** In your sheet, click **Share**. Under General access pick **Anyone with the link** and **Viewer**. Click **Done**.
- 3** **Make your board link.** On the computer hooked to your TV, go to **boards.wackymclovin.com**. Scroll to **Using your own copy of a sheet**. Paste your sheet link, pick your game, click **Make my link**.
- 4** **Open it and bookmark it.** Click **Open**. Bookmark the page. Press **F11** (Windows) or **Control + Command + F** (Mac) for full screen.
- 5** **Test it.** On your phone, open your sheet. Type a name next to spot 1. Look at the TV. It shows up in about 5 seconds.
- 6** **Set up your shot.** TV behind you. Phone on the tripod in front of you. Light in front of you.
- 7** **Fix glare and blur.** TV brightness to about 60%. On iPhone, tap and hold the TV on your camera screen to lock focus.
- 8** **Go live.** Open TikTok, tap **+**, swipe to **LIVE**, add a title, and tap **Go LIVE**.

GOOD TO KNOW

If your Wi-Fi blips, the board keeps showing the last good info and catches up when you're back.

4 *Your sheet, made simple*

You only ever type in the sheet. The board does the rest.

GAME TABS: AUCTION, \$10, \$30

	A	B	C	D	E
1	SPOT	OWNER	BID	NOTE	ORDER
2	1	ripping	\$14		#1790
3	2	cardqueen	FREE	winner	
4	3				

B: the buyer's name. **C:** their bid (auction only), or **FREE**. **D:** type **winner** to tag a winner. **E:** filled in by shop orders.

CHASE TABS: AUCTION_CHASE, \$10_CHASE, \$30_CHASE

A (DON'T CHANGE)	B (TYPE HERE)
Chase Image URL	a picture link (see below)
Chase Name	Alt Art Chase Card
Chase Value	\$450 CARD
Title / Subtitle / Price	WACKY HUNT / PRE-FILL / \$10 A SPOT
Box / Banner / Status	OP-11 Booster Box / Every spot gets a pack / LIVE

Change the chase and the board plays a reveal. Want more than one? Add rows named **Chase 2 Image URL**, **Chase 2 Name**, **Chase 2 Value** (up to 4).

5 *Pictures and new games*

Show off your prizes, and start fresh without losing the last game.

GETTING A PICTURE LINK

- 1 Open **boards.wackymclovin.com/picture**.
- 2 Drag the product photo onto the page (or paste a link). Wait for the green check.
- 3 Click **Copy link** and paste it into the picture box.

Your own photo? Upload it to Google Drive, share it as **Anyone with the link**, and paste that link.

STARTING A FRESH GAME

- 1 Right-click the tab (like **\$10**) and pick **Duplicate**. Rename it, like **9_20_26_\$10**. Clear column B.
- 2 Open the **LIVE** tab. Type the new tab name next to **\$10**. The board switches in a few seconds.

RIP TILL YOU HIT **RTYH**

LIVE **\$6 / PACK**

RIPPING NOW

wingtip56
Pack
4
\$24 so far

UP NEXT: PACKMASTER, CARDQUEEN

HIT = Illustration Rare or better

HIT BOARD

3 HITS	6.7 AVG PACKS	2 LUCKIEST: MADCITY44
untapped_potentialtcg 11 PK Mew IR		
madcity44 2 PK Pikachu IR		
dolo_khaii 7 PK Charizard ex SIR		

6 *The 8 games*

Pick the board that matches the break you're running.

MAIN SHEET

\$1 START AUCTION

Spots with bids. The high bidder gets a gold crown. Uses the AUCTION tab.

MAIN SHEET

\$10 PRE-FILL

Spots turn green as they sell. Shows how many are left. Uses the \$10 tab.

MAIN SHEET

\$30 A PACK

Same idea as pre-fill, set up for pack sales. Uses the \$30 tab.

MAIN SHEET

CUSTOM AUCTION

Click Settings on the board to pick any tab, how many spots, and the words.

OWN SHEET

RIP TILL YOU HIT

Big pack counter. Add each buyer at the bottom. Type the hit card and the board yells HIT!

OWN SHEET

PICK YOUR TYPE

A color grid. Type the buyer next to their type or color.

OWN SHEET

CASE BREAK

Shows every box (sealed, ripping, done), 24 spots, and a live hit list.

OWN SHEET

WALL OF HITS

Spotlights the newest big pull and shows the whole night's hits.

ONLY TYPE IN TWO PLACES

The **yellow boxes** and the **rows under the gold headers**. Leave everything else alone and the board always works.

Game tips and rules

What to do during the stream, and how to stay on the right side of the rules.

QUICK TIPS FOR EACH GAME

GAME	WHAT TO DO DURING THE STREAM
Rip Till You Hit	Change PACKS as you open. Type the HIT CARD when it lands. The next person in line moves up by themselves.
Pick Your Type	COLOR can be a word (red, fire, water) or a code like #ff8800. Add HITS like "2 SIR" if you want.
Case Break	Set each box to sealed , ripping , or done . Add hits at the bottom of the hit list.
Wall of Hits	Add every big pull at the bottom with a picture link. The newest gets the spotlight.
Any game	Add ?sound=1 to the board address for a chime on each hit.

PLAY BY THE RULES


TikTok Shop allows personal breaks, pick your team or type, pull till you win, and case breaks. It bans bounties, pull games, King of the Hill, random teams, drafts, and points breaks.

Whatnot doesn't allow prizes that depend on what gets pulled. Bonus items are fine when every buyer is sure to get them and you say so up front.

Rules change. Check each app's break rules before you run a new game. Always show the box, what each spot gets, and the price before anyone buys.

8 *Shop orders and spot labels*

Sell spots in your shop. The board and the labels take care of themselves.



WE SET THIS UP WITH YOU

This part connects to your own Shopify store, so we set it up with you once. TikTok Shop orders flow into Shopify when your TikTok Shop is connected to it. After setup, it runs by itself.

ONE-TIME SETUP

- 1** **Make a product for each game you sell**, like "Wacky \$10 Spot". Turn on inventory tracking and set it to **24**. Now you can't oversell the board.
- 2** **Fill in the SHOP tab**. Column A: part of the product name. Column B: the board (**AUCTION** , **\$10** , **\$30** , **TYPES** , **CASE** , or **RTYH**). Column D: **YES** .
- 3** **Pick Your Type?** Make the product options match your types (Fire, Water, Grass). Buyers land on the type they picked.
- 4** **Open the Print Station** at **boards.wackymclovins.com/print** on the computer with your label printer. Pick your label size. Click **Print a test label**.
- 5** **Do a pretend order**. Type **YES** next to **Test Order** in the SHOP tab. In about a minute, **TEST BUYER** lands on the board and a label prints. Delete the test name after.


9 *Printing spot labels*

Set the printer once. Every shop spot prints by itself.

PRINT LABELS WITH NO POP-UP

COMPUTER	DO THIS ONCE
Mac	Quit Chrome. Open the Terminal app. Paste this and press Enter: <code>open -na "Google Chrome" --args --kiosk-printing https://boards.wackymclovin.com/print/</code>
Windows	Right-click your Chrome shortcut, pick Properties. At the end of Target , add a space and <code>--kiosk-printing</code> . Click OK and open Chrome from that shortcut.
Both	Make your label printer the default printer.

WHAT'S ON EACH LABEL



The board name, a giant spot number, the buyer, the order number, and the time.

Stick the label on the buyer's pack or top loader as you rip. That's how you keep every spot straight.

If a board is full, the label says **NO OPEN SPOT - CHECK** so you can fix it by hand.

Label sizes on the Print Station: 4x6, 4x3, 2.25x1.25 (DYMO), 2x1, and 62x29mm (Brother).

HEADS UP

TikTok hides some buyer details. If there's no name, the label shows the order number instead. The spot still belongs to that order.

10 Quick fixes

Something off? Find it here. Most fixes take a few seconds.

PROBLEM	FIX
Board says it can't read the sheet	Share the sheet: Anyone with the link, Viewer.
I typed a name and nothing changed	Wait 5 seconds. Check you're in the right tab (look at the LIVE tab). Spot number in A, name in B.
Prize picture won't show	Use the Picture Link Maker. Drive photos must be shared with anyone with the link.
Board looks blurry on stream	Lock focus on the TV. Lower brightness. Turn off motion smoothing.
Shop order didn't show up	Check Last Checked in the SHOP tab. The product name must match a SHOP row set to YES. Orders count once they're paid.
Label didn't print	Keep the Print Station open with Auto print ON. Make the label printer your default. Try a test label.

BEFORE EVERY STREAM (30 SECONDS)

- ☐ Board open, full screen, showing the right game
- ☐ Chase picture and prize are set
- ☐ Phone plugged in, focus locked, Do Not Disturb on
- ☐ Print Station open (if you sell spots in your shop)

More help: boards.wackymclovin.com/how-to · **Shop:** wackymclovin.com